

Package: FluxSeparator (via r-universe)

June 5, 2026

Title Separation of Diffusive and Ebullitive Fluxes

Version 2.0.1

Description Separates diffusive and ebullitive (bubble) fluxes from continuous concentration measurements using a running variance approach. Ebullitive events are identified when the running variance exceeds a user-set threshold. Diffusive fluxes are calculated via linear regression on the non-ebullitive portion of the data. See Sjø et al. (2024) <[doi:10.1029/2024JG008035](https://doi.org/10.1029/2024JG008035)> for details.

License MIT + file LICENSE

URL <[link href="https://cran.r-project.org/web/packages/FluxSeparator/"](https://cran.r-project.org/web/packages/FluxSeparator/)>, <[link href="https://github.com/JonasStage/FluxSeparator/"](https://github.com/JonasStage/FluxSeparator/)> rel = canonical">

BugReports <https://github.com/JonasStage/FluxSeparator/issues>

Encoding UTF-8

Roxygen list(markdown = TRUE)

RoxygenNote 7.3.3

Depends R (>= 4.1.0)

Imports broom, dplyr, DT, ggplot2, ggpubr, graphics, HMR, lubridate, magrittr, purrr, readr, rlang, shiny, shinydashboard, stats, stringr, tidyr, TTR, patchwork

Suggests knitr, rmarkdown, testthat (>= 3.0.0)

VignetteBuilder knitr

Config/testthat/edition 3

LazyData true

Config/pak/sysreqs cmake make libicu-dev libuv1-dev libssl-dev libx11-dev zlib1g-dev

Repository <https://jonasstage.r-universe.dev>

Date/Publication 2026-06-05 13:02:16 UTC

RemoteUrl <https://github.com/jonasstage/fluxseparator>

RemoteRef HEAD

RemoteSha b43bd6915045e4ad496b406717846a480014f493

Contents

FluxSeparator-package	2
diffusive_flux	2
DIY_sensor_data	6
ebullitive_flux	7
FluxSeparatorApp	9
ppm_to_umol	10
read_CH4_files	11

Index **13**

FluxSeparator-package *FluxSeparator: Separation of Diffusive and Ebullitive Fluxes*

Description

Separates diffusive and ebullitive (bubble) fluxes from continuous concentration measurements using a running variance approach.

Author(s)

Jonas Stage Sjø <Jonassoe@biology.sdu.dk>

diffusive_flux *Diffusive flux*

Description

Separates the diffusive and ebullitive fluxes, to calculate the diffusive flux, as a linear function of concentrations over time. This is done by firstly finding all events that are considered ebullitive (for more info see [ebullitive_flux](#)).

Several factors can be set to determine what is considered ebullitive events, remove observations before doing diffusive flux, number of observations used in the diffusive flux calculation, cutoffs if concentrations start too high and number of observations needed in the linear model.

Output data is converted to concentration change per hour.

Usage

```
diffusive_flux(
  data,
  concentration_values = "pred_CH4",
  runvar_cutoff = 0.5,
  remove_observations_prior = 200,
  number_of_observations_used = 400,
  show_plots = TRUE,
  IndexSpan = 30,
  cutoff_start_value = Inf,
  number_of_observations_required = 50,
  number_of_pumpcycles_in_plot = 50,
  smooth_data = FALSE,
  look_for_bubbles = TRUE,
  Hutchinson_Mosier_correction = FALSE,
  volume,
  area,
  min_obs_per_cycle = 100,
  time_gap_seconds = 30,
  runvar_window = 5,
  smooth_window = 10
)
```

Arguments

<code>data</code>	Your data frame. Must contain columns <code>datetime</code> , <code>PumpCycle</code> , <code>station</code> , and <code>tempC</code> .
<code>concentration_values</code>	Name of your variable representing the concentration.
<code>runvar_cutoff</code>	Cutoff of the running variance, which is used to determine if an increase in concentration is an ebullitive event. Lower values increases number of ebullitive events registered.
<code>remove_observations_prior</code>	Remove n number of observations before calculating the diffusive flux by a linear slope.
<code>number_of_observations_used</code>	Number of observations used to calculate the diffusive flux by a linear slope.
<code>show_plots</code>	Show plots which can assist in the determination of good fits for the model. A boolean variable which should be <code>TRUE</code> or <code>FALSE</code> .
<code>IndexSpan</code>	Number of observations which are included before and after an ebullitive event, to ensure the entire event is determined.
<code>cutoff_start_value</code>	Variable indicating what the maximum starting concentration can be. Defaults to <code>Inf</code> (no filtering).
<code>number_of_observations_required</code>	Number of observations required in each cycle for the function to compute a linear model on the data.

number_of_pumpcycles_in_plot	Number of cycles which are plotted. Used only if show_plots = TRUE.
smooth_data	Computes a running mean on the concentration data five times, to smoothen data if data is low bit resolution. See Sjø et al. (2023) for more information.
look_for_bubbles	Can be used for the function to not consider ebullitive events. Can be useful when calculating diffusive CO2 flux.
Hutchinson_Mosier_correction	Can be used to correct flux measurements based on the Hutchinson-Mosier correction (1981). However, fluxes are only calculated of three points. A boolean variable which should be TRUE or FALSE.
volume	Volume of the chamber used for calculating fluxes (L). This is only needed if Hutchinson_Mosier_correction = TRUE.
area	Surface area of the chamber used for calculating fluxes (m^2). This is only needed if Hutchinson_Mosier_correction = TRUE.
min_obs_per_cycle	Minimum number of observations per pump cycle to include in analysis (default 100).
time_gap_seconds	Time gap in seconds used to separate event groups when detecting bubbles (default 30).
runvar_window	Window size for the running variance calculation (default 5).
smooth_window	Window size for the running mean smoothing passes (default 10). Only used when smooth_data = TRUE.

Value

A data frame containing the following:

- station - The station from the input data
- PumpCycle - Cycle number
- datetime_start - Start time of the cycle
- datetime_end - End time of the cycle
- slope_concentration_hr - The diffusive flux per hour ($ppm h^{-1}$)
- slope_standard_error - The standard error of the flux
- n_obs_included_in_lm - Number of observations used to calculate the diffusive flux
- r2 - Variance explained by the linear model
- temp - Average temperature within the chamber (C)
- hmr_slope - Flux calculated using the HMR package ($ppm h^{-1}$). This is only returned if the method selected by the HMR package is either *Hutchinson-Mosier correction* or *No flux*, in case of *LR* used the function will return NA. Only given if the Hutchinson-Mosier correction is calculated.
- hmr_se - Standard error of the *hmr_slope*. This is only returned if the *hmr_slope* is calculated.

- `hmr_pvalue` - The p-value for the null hypothesis of zero flux. This is only returned if the `hmr_slope` is calculated.
- `hmr_lower95` - The lower end-point of the 95\ for the flux. This is only returned if the `hmr_slope` is calculated.
- `hmr_upper95` - The upper end-point of the 95\ for the flux. This is only returned if the `hmr_slope` is calculated.
- `method` - The method used by the HMR package to calculate flux. This is only returned if the `hmr_slope` is calculated.

When `show_plots = TRUE`, the returned data frame carries an attribute "plots" containing a list of **ggplot2** objects.

Author(s)

Jonas Stage Sørensen <Jonassoe@biology.sdu.dk>

References

Sørensen et al. (2024). Self-Made Equipment for Automatic Methane Diffusion and Ebullition Measurements From Aquatic Environments. doi:10.1029/2024JG008035.

Sørensen et al. (2023). Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. doi:10.1016/j.scitotenv.2023.162895.

Hutchinson, G.L. and Mosier, A.R. (1981). Improved soil cover method for field measurement of nitrous oxide fluxes. Soil Science Society of America Journal, 45, pp. 311-316.

Pullens, J.W.M., Abalos, D., Petersen, S.O. and Pedersen, A.R. (2023). Identifying criteria for greenhouse gas flux estimation with automatic and manual chambers: A case study for N₂O. European Journal of Soil Science, 74, e13340. doi:10.1111/ejss.13340.

See Also

[ebullitive_flux](#), [ppm_to_umol](#)

Examples

```
library(FluxSeparator)

data(DIY_sensor_data)

DIY_sensor_data %>%
  diffusive_flux(cutoff_start_value = 450, show_plots = TRUE)
# 450 would be good for CO2, while 5 could be good for CH4
```

`DIY_sensor_data`*Data from Lake Lyng*

Description

A subset of data from the paper Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. One measurement containing only diffusive flux and one containing ebullitive events.

Usage`DIY_sensor_data`**Format**

A data frame with 2,201 rows and 12 variables:

datetime Date and time of measurement

RH Relative humidity (percent)

tempC Temperature in degrees Celsius

CH4smV Methane sensor voltage

K33_RH Relative humidity measured by the CO2 sensor

K33_Temp Temperature in degrees Celsius measured by the CO2 sensor

K33_CO2 CO2 concentration in ppm

SampleNumber Sample number in this pump cycle

PumpCycle Pump cycle which counts upwards after the chamber has been flushed

pred_CH4 Predicted methane concentration, calculated using the `read_CH4_files` function and calibration values

station Station name, needed for diffusive and ebullitive flux calculations

sensor Sensor identification number

Source

Sø et al. (2023). Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. [doi:10.1016/j.scitotenv.2023.162895](https://doi.org/10.1016/j.scitotenv.2023.162895)

Examples

```
data(DIY_sensor_data)
head(DIY_sensor_data)
```

ebullitive_flux	<i>Ebullitive flux</i>
-----------------	------------------------

Description

Separates the diffusive and ebullitive fluxes, to calculate the ebullitive flux, as the change in concentration from ebullitive events. This is done by computing a running variance; if the running variance exceeds a customizable cutoff value it is considered an ebullitive event.

Additional factors can be set to determine what is considered ebullitive events. Output data is converted to concentration change per hour.

Usage

```
ebullitive_flux(
  data,
  concentration_values = "pred_CH4",
  top_selection = "last",
  runvar_cutoff = 0.5,
  show_plots = TRUE,
  IndexSpan = 30,
  concentration_diffusion_cutoff = 1,
  number_of_pumpcycles_in_plot = 24,
  smooth_data = FALSE,
  min_obs_per_cycle = 100,
  time_gap_seconds = 30,
  runvar_window = 5,
  smooth_window = 10
)
```

Arguments

data	Your data frame. Must contain columns datetime, PumpCycle, station, and tempC.
concentration_values	Name of your variable representing the concentration.
top_selection	Can be set to "last" or "max" to either use the last or maximum concentration value in each ebullitive event.
runvar_cutoff	Cutoff of the running variance, which is used to determine if an increase in concentration is an ebullitive event. Lower values increase the number of ebullitive events registered.
show_plots	Show diagnostic plots. A logical; defaults to TRUE.
IndexSpan	Number of observations which are included before and after an ebullitive event, to ensure the entire event is captured.
concentration_diffusion_cutoff	Minimum concentration change that is considered an ebullitive event.

number_of_pumpcycles_in_plot	Number of cycles which are plotted. Used only if show_plots = TRUE.
smooth_data	Computes a running mean on the concentration data five times, to smooth data if data is low bit resolution. See Sjø et al. (2023) for more information.
min_obs_per_cycle	Minimum number of observations per pump cycle required for processing (default 100).
time_gap_seconds	Time gap in seconds used to separate bubble event groups (default 30).
runvar_window	Window size for the running variance computation (default 5).
smooth_window	Window size for each running-mean smoothing pass (default 10). Only used when smooth_data = TRUE.

Value

A data frame containing the following:

- station
The station column from the input data
- PumpCycle
Cycle number
- datetime_start
Start time of the cycle
- datetime_end
End time of the cycle
- sum_bubbles_concentration
The sum of the differences in concentration caused by bubbles
- n_bubbles
Number of bubbles detected. Bear in mind that this function has difficulties detecting the number of bubbles if they are close to each other
- pumpcycle_duration_hr
Length of the cycle duration in hours
- temp
Average temperature within the chamber
- bubbles_per_time
Amount of bubbles divided by the duration of the cycle in hours
- concentration_per_time
Ebullitive flux, as the sum of concentration change divided by the duration in hours

When show_plots = TRUE, a "plots" attribute is attached to the result containing a list of **ggplot2** objects.

Author(s)

Jonas Stage Sjø <Jonassoe@biology.sdu.dk>

References

Sø et al. (2024). Self-Made Equipment for Automatic Methane Diffusion and Ebullition Measurements From Aquatic Environments. doi:10.1029/2024JG008035.

Sø et al. (2023). Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. doi:10.1016/j.scitotenv.2023.162895.

See Also

[diffusive_flux](#), [ppm_to_umol](#)

Examples

```
library(FluxSeparator)

data(DIY_sensor_data)

DIY_sensor_data %>%
  ebullitive_flux()
```

FluxSeparatorApp

FluxSeparator Shiny App

Description

Shiny app to visualize the process of separating diffusive and ebullitive fluxes. The app also gives the user the ability to mark areas where diffusive fluxes should be calculated.

Usage

```
FluxSeparatorApp(...)
```

Arguments

... Additional arguments passed to [shinyApp\(\)](#).

Author(s)

Jonas Stage Sø <Jonassoe@biology.sdu.dk>

References

Sø et al. (2024). Self-Made Equipment for Automatic Methane Diffusion and Ebullition Measurements From Aquatic Environments. doi:10.1029/2024JG008035.

Sø et al. (2023). Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. doi:10.1016/j.scitotenv.2023.162895.

Hutchinson, G.L. and Mosier, A.R. (1981). Improved soil cover method for field measurement of nitrous oxide fluxes. *Soil Science Society of America Journal*, 45, pp. 311-316.

Pullens, J.W.M., Abalos, D., Petersen, S.O. and Pedersen, A.R. (2023). Identifying criteria for greenhouse gas flux estimation with automatic and manual chambers: A case study for N₂O. *European Journal of Soil Science*, 74, e13340. doi:10.1111/ejss.13340.

See Also

[diffusive_flux](#), [ebullitive_flux](#), [ppm_to_umol](#)

Examples

```
library(FluxSeparator)
```

```
FluxSeparatorApp()
```

ppm_to_umol

ppm_to_umol

Description

Conversion of $ppmV$ to $\mu mol m^{-2} h^{-1}$ using the ideal gas law.

Usage

```
ppm_to_umol(pressure, concentration, volume, temperature_C, area)
```

Arguments

pressure	Air pressure during measurement (Pa).
concentration	Concentration of the gas in ppm ($\mu mol/mol$).
volume	Volume of the chamber used for measuring in m^3 .
temperature_C	Temperature in degrees Celsius in the chamber.
area	Surface area of the chamber used in m^2 .

Value

A numeric vector of flux values in $\mu mol m^{-2} h^{-1}$.

Author(s)

Jonas Stage Sørensen <Jonassoe@biology.sdu.dk>

Examples

```
# Convert a single value
ppm_to_umol(pressure = 101325, concentration = 10,
            volume = 0.01, temperature_C = 20, area = 0.05)
```

read_CH4_files	<i>read_CH4_files</i>
----------------	-----------------------

Description

A function to ease the import of data from DIY sensors, which reads a CSV file, calculates the absolute humidity, V0, RsR0, and the methane concentration.

Usage

```
read_CH4_files(data, files, join_model_coef = TRUE, model_coef_data = NULL)
```

Arguments

data	A data frame containing the path, sensor identification, and model coefficients for this specific sensor. Model coefficients can also be read in as a separate data frame and defined in the <code>model_coef_data</code> variable.
files	A vector supplying the path to the file being read.
join_model_coef	Boolean variable. Join data with dataframe <code>model_coef_data</code> to convert sensor voltage signal to methane concentration.
model_coef_data	Data frame consisting of the calibration values used to convert sensor voltage signal to methane concentration. Required when <code>join_model_coef = TRUE</code> .

Value

A data frame output including all the original values, with the exception of the model coefficients.

pred_CH4 Computed from the calibration model. The CH4 concentration calculated from the sensor resistance, expressed in ppm.

Author(s)

Jonas Stage Sørensen <Jonassoe@biology.sdu.dk>

References

Sørensen et al. (2023). Methane and carbon dioxide fluxes at high spatiotemporal resolution from a small temperate lake. [doi:10.1016/j.scitotenv.2023.162895](https://doi.org/10.1016/j.scitotenv.2023.162895)

Sørensen et al. (2024). Self-Made Equipment for Automatic Methane Diffusion and Ebullition Measurements From Aquatic Environments. [doi:10.1029/2024JG008035](https://doi.org/10.1029/2024JG008035)

See Also

[ebullitive_flux](#), [diffusive_flux](#), [ppm_to_umol](#)

Examples

```
## Not run:
library(FluxSeparator)

# read in model coef
model_coef <- read_csv("model_coef.csv")

# path to DIY sensors files
path_to_files <- list.files(pattern = ".csv")

# create data frame for path, sensor and station.
data_path <- tibble(path = path_to_files,
                    sensor = c(1, 2, 3, 4),
                    station = c(1, 2, 4, 3))

# join with model_coef and calculate CH4 in ppm.
read_CH4_files(data_path, path,
              model_coef_data = model_coef)

#### Example using join_model_coef = FALSE ####

# join with model_coef.
joined_data_path <- left_join(data_path, model_coef, by = join_by(sensor))

# calculate CH4 in ppm.
read_CH4_files(joined_data_path,
              path,
              join_model_coef = FALSE)

## End(Not run)
```

Index

* datasets

DIY_sensor_data, [6](#)

diffusive_flux, [2](#), [9](#), [10](#), [12](#)

DIY_sensor_data, [6](#)

ebullitive_flux, [2](#), [5](#), [7](#), [10](#), [12](#)

FluxSeparator (FluxSeparator-package), [2](#)

FluxSeparator-package, [2](#)

FluxSeparatorApp, [9](#)

ppm_to_umol, [5](#), [9](#), [10](#), [10](#), [12](#)

read_CH4_files, [11](#)

shinyApp, [9](#)